

B	6	
A #	6	
A	6	Tab-Play (OFF = Vel. 1-63, ON = Vel. 64-127)
G #	6	Open String First Toggle (OFF = Vel. 1-63, ON = Vel. 64-127)
G	6	FX Sound: Hit Rim (<i>Acoustic</i>) / Random Noise (<i>Electric</i>)
F #	6	FX Sound: Hit Top Mute (<i>Acoustic</i>) / Dead Note Upstroke (<i>Electric</i>)
F	6	FX Sound: Hit Top Open (<i>Acoustic</i>) / Pick Scrape (<i>Electric</i>)
E	6	Poly Repeater 2
D #	6	Auto Legato (HP = Vel. 1-63, SL = Vel. 64-127)
D	6	Poly Repeater 1
C #	6	Strummer Toggle (OFF = Vel. 1-63, ON = Vel. 64-127)
C	6	FX Sound: Upstroke Sound 2
B	5	FX Sound: Downstroke Sound 2
A #	5	FX Sound: Upstroke Sound 1
A	5	FX Sound: Downstroke Sound 1
G #	5	FX Sound: Silence-Stroking
G	5	FX Sound: Silence-Pressing
F #	5	FX Sound: Silence-Slapping
F	5	FX Sound: Scratch
E	5	
D #	5	
D	5	Chord Detect / Select Toggle (SELECT = Vel. 1-63, DETECT = Vel. 64-127)
C #	5	Strum Time (Higher velocity = shorter strum time)
C	5	
B	4	Muted Up: Full, Mediant, Treble
A #	4	
A	4	Muted Down: Mediant, Treble
G #	4	
G	4	Muted Down: Full, Bass
F #	4	Mute Voice 2
F	4	Mute Voice 1
E	4	Open Up: Full, Mediant, Treble
D #	4	Strummer SEQ 8
D	4	Open Down: Mediant, Treble
C #	4	Strummer SEQ 7
C	4	Open Down: Full, Bass
B	3	1. String: e'
A #	3	Strummer SEQ 6
A	3	2. String: b
G #	3	Strummer SEQ 5
G	3	3. String: g
F #	3	Strummer SEQ 4
F	3	4. String: d
E	3	5. String: A
D #	3	Strummer SEQ 3
D	3	6. String: E
C #	3	Strummer SEQ 2
C	3	Strummer SEQ 1
B	2	Select Chord 12
A #	2	Select Chord 11
A	2	Select Chord 10
G #	2	Select Chord 09 · Capoman Fret 16
G	2	Select Chord 08 · Capoman Fret 15
F #	2	Select Chord 07 · Capoman Fret 14
F	2	Select Chord 06 · Capoman Fret 13
E	2	Select Chord 05 · Capoman Fret 12
D #	2	Select Chord 04 · Capoman Fret 11
D	2	Select Chord 03 · Capoman Fret 10
C #	2	Select Chord 02 · Capoman Fret 09
C	2	Select Chord 01 · Capoman Fret 08
B	1	Capoman Fret 07
A #	1	Capoman Fret 06
A	1	Capoman Fret 05
G #	1	Capoman Fret 04
G	1	Capoman Fret 03
F #	1	Capoman Fret 02
F	1	Capoman Fret 01
E	1	Capoman Fret 00
D #	1	
D	1	
C #	1	Capoman Switch + E1-G#2
C	1	Strman 1. String: e'
B	0	Strman 2. String: b
A #	0	Strman 3. String: g
A	0	Strman 4. String: d
G #	0	Strman 5. String: A
G	0	Strman 6. String: E
F #	0	
F	0	HP (Hammer On & Pull Off (E1 - C5) Poly Legato
E	0	LS (Legato Slide (F1 - C5) Poly Legato
D #	0	SIO (Slide In & Out: F#1 - C5)
D	0	PM (Palm Mute: E1 - C5)
C #	0	NH (Natural Harmonics D2 - C5)
C	0	SUS (Sustain E1 - C5)

Strummer Zone

Chord Detection Zone